

---


# NHM Tutorial

## Part. III. Realistic Simulations

Syugo HAYASHI

(Forecast Research Department /  
Meteorological Research Institute)





# Overall Index (Tutorial\_0~3)

- 0. What is the NHM?
  - *NHM\_Tutorial\_0.ppt*
- 1. Brief usage of the NHM
  - *NHM\_Tutorial\_1.ppt*
- 2. Practical Exercise
  - *NHM\_Tutorial\_2.ppt*, ***NHM\_Tutorial\_3.ppt (this file)***
    - 2.0 Installation of the NHM
      - prepare the external files, compile the model and tools, and install the visualization tools
    - 2.1. Idealized Experiments
    - **2.2. Realistic Experiments**





## 2. Practical Exercise

### 2.2. Realistic Experiments

- Realistic Weather Simulation Using Global analysis (or forecast) data and GTOPO30 as topography.
- We can use the following dataset.
  - **NCEP-GFS forecast** and analysis
  - JRA25 (JMA-25yr-reanalysis)  
& JCDAS (semi-realtime reanalysis)
  - JMA global model data supplied by the Japan Meteorological Business Support Center (JMBSC)





# Available Global Dataset for the NHM

Data Set	Period	Resolution	File format
<b>NCEP GFS Forecast</b>	2007Apr ~ now (the last 6 months?)	1.0 x 1.0 degree global every 6hr, 180hr/3hr forecast	GRIB
NCEP GFS Analysis	2004Mar ~ last month	1.0 x 1.0 degree global every 6hr	GRIB
<b>JRA25</b> (& JCDAS)	<b>1979Jan ~ now</b>	1.25 x 1.25 degree global every 6hr	GRIB
JMBS ( <b>JMA GSM Forecast</b> ) (not including land-surface, sst and soil data)	2004Apr ~ 2007Nov20	1.25 x 1.25 degree global (thinned grid) every 6hr	GRIB
	2007Nov21 ~ now	0.5 x 0.5 degree global every 6hr	GRIB2

- Of course, NuSDaS formatted data from JMA are available. But they are not able to be downloaded freely.  
(e.g. Meso-Analysis, Global-Analysis, Global-forecast in NuSDaS)





---

# Nhm/Tools/grib2nus including Download and Convert tools

- (See “README” file)
- step 1. Configure
- (This tools need compiled pnusdas)
- `$> sh configure -c ../../Module/Mk/config/pc/config.[xxx]`
  
- step 2. make load-module for convertor
- `$> make`





# Nhm/Tools/grib2nus including Download and Convert tools

- step 3. get data (JMBSC, NCEP1d\_fct, NCEP1d\_anl or JRA25)
  - Change date in the “**TIMECARD**” <- initial time  
yyyy mm dd hh min
  - “**get\_ncep1d\_anl.sh**”, “**get\_ncep1d\_fct.sh**”, “**get\_jra.sh**” and “**get\_jmbsc.sh**” are prepared.
  - In default setting, these shells download the files for 48hr-forecast. As to your needs, you have to change the range of forecast for saving the download time. It is written in the head of each shell script.
  - save files at Nhm/Data/ncep1d\_fct(or jra, jmbsc)/\${DATE:yyyymmddhhmn}





## Nhm/Tools/grib2nus including Download and Convert tools

- step 4. convert GRIB(or GRIB2) data to NuSDaS
  - “**jmbsc2nus.sh**”, “**jra2nus.sh**”, “**ncep1d2nus\_anl.sh**” and “**ncep1d2nus\_fct.sh**” are prepared.
  - Don’t change **TIMECARD** when you download the dataset.
  - And these shell scripts expect that the downloaded files are located at “Nhm/Data/ncep1d\_fct(or jra, jmbsc)/\${DATE:yyymmddhhmn}” which is the default value of the download tools.
  - NuSDaS files are output into the same directory at the downloading. (“fcst\_p.nus”, “fcst\_sfc.nus” are made.)





## Nhm/Ss/RF20km

- (See “README” file)
- Edit "**TIMECARD**" same as downloaded DATE
- Edit "**parm.sh**" for your environments
- Select the appropriate "**pre.sh**" in "**all.sh**" for the downloaded data.
- And run the "**all.sh**". show the contents of all.sh
  - \$> sh setup.sh # set directories, etc
  - \$> sh mcnst.sh # make orography file
  - \$> sh mksfccnst.sh # make surface constant files like albedo, etc
  - \$> sh pre\_jmbosc.sh [pre\_jra.sh, pre\_ncep1d\_anl.sh, pre\_ncep1d\_fct.sh]  
# make initial and boundary files
  - \$> sh fcst.sh (**attention! Check MPI process number**) # start the forecast
  - \$> sh end.sh # move result files
- (And you can execute 1-way nesting-run in 5km (or more fine mesh) by using the results of RF20km )





# Nhm/Ss/RF20km/parm.sh

- Edit parm.sh for your environments
  - # directory
  - **DIRNAME=RF20km** **#set experiment name**
  - **NHMDIR=/home/seasia/Nhm** **#set your \${NHM} directory**
  - MYDIR=\${NHMDIR}
  - BINDIR=\${MYDIR}/Module/Bin
  - **SHDIR=\${MYDIR}/Ss/\${DIRNAME}**
  - CSTDIR=\${MYDIR}/Const
  - PARMDIR=\${MYDIR}/Parm/\${DIRNAME}
  - TOPODIR=\${MYDIR}/Data/\${DIRNAME}
  - JGWKDIR=\${MYDIR}/Work/\${DIRNAME}
  - DATADIR=\${MYDIR}/Data/\${DIRNAME}
  - INPUTDIR=\${MYDIR}/Tools/grib2nus/data





# Nhm/Ss/RF20km/parm.sh

- Edit parm.sh for your environments
  - # model parameters
  - **IDT=75** # set dt about dx (in km) \* 3~5 & can divide 600
  - **FTEND=12** # forecast hour
  - **KTDEL=3** # interval hour of boundary file  
"6" for JMBSC, JRA, NCEP\_anl. "3" for NCEP\_fct
  - # ---- parameter for domain
  - **NX=201** # grid number in x-direction
  - **NY=201** # grid number in y-direction
  - **NZ=40** # grid number in z-direction





# Nhm/Ss/RF20km/parm.sh

- Edit parm.sh for your environments
  - **NPROJC='MER ' # map projection (in south-hemisphere, "MER" only)**
    - "LMN" and "PSN" are available. Don't change "4 digit character".
  - **DX=20000.0000 # horizontal resolution in x-direction**
  - **DY=20000.0000 # horizontal resolution in y-direction**
  - **MDLTOP=23000. # model top height in (m)**
  - **SLAT=0.000000 # standard latitude only for map projection**
  - **SLON=150.000000 # standard longitude only for map projection**
  - FLATC=-999.999878 # not used
  - FLONC=-999.999878 # not used
  - **XI=100.000000 # x-grid point of true Lat. and Lon.**
  - **XJ=100.000000 # x-grid point of true Lat. and Lon.**
  - **XLAT=0.000000 # true latitude at (XI, XJ)**
  - **XLON=150.000000 # true longitude at (XI, XJ)**
  - It is easy to set (XI, XJ) at center grid number and (XLAT, XLON) at center lat & lon.
  - GRMAX=0.15
  - MODE\_ZS\_SMOOTH='1.5 average'





# Nhm/Ss/RF20km/parm.sh

- Edit parm.sh for your environments
  - #parameter for boundary dumping area
  - **automatically** set 4% of domain size, respectively.
  - **IWDTH=6 #domain of just using topography of outer model**
  - **IMERG=6 #domain of merging topography between outer model and inner model**
  - **IDIFX=`expr \$IWDTH + \$IMERG`**
  - #start level of Rayleigh dumping : about  $NZ * 0.8$
  - **automatically** set 80% of grid number in vertical.
  - **KZDST=32**
- **End edit parm.sh**





# Nhm/Ss/RF20km/

setup.sh, mkenst.sh, mkfscnst.sh, pre\_[jbmsc].sh

- setup.sh
  - **automatically** make domain card and work directory from “parm.sh”.
  - **automatically** set NuSDaS\_definition files from “parm.sh”.
- mkenst.sh
  - **automatically** make topographic data (mftopo) from GTOPO30
- mkfscnst.sh
  - **automatically** make land surface parameter file, if it is needed.
- pre\_[jbmsc].sh
  - **automatically** make initial and boundary files.
  - output files; mfin(initial file), mfex(boundary file), ptgrd (surface parameter), mfhm(topographic data), [sst (for self-nesting)]





# Nhm/Ss/RF20km/fcst.sh

- “fcst.sh” includes namelists for the setting of the NHM
  - link constant files
  - preparing the NuSDaS output
  - read the namelist for the NHM
    - If you want to change the namelists, re-write here.
    - The details of the namelist are describes in **“[Doc/En/namelist/fcst.sh\\_namelist.html](#)”**
  - execute the NHM (with MPI, check MPI-process!)
  - output the forecast





# Nhm/Ss/RF20km/end.sh

- “end.sh”
  - Move output data to output directory.
    - ->DATADIR=\${MYDIR}/Data/\${DIRNAME}
    - If the "DATADIR" already exist, automatically change the name of pre-exist directory and then move new results.
  - Clean up work directory





# Start forecast!

- At the first time, execute each shell script in "all.sh" step by step.
  - \$> sh setup.sh
  - \$> sh mkcnst.sh
  - \$> sh mksfccnst.sh
  - \$> sh pre\_jmbsec.sh [or, pre\_jra.sh, pre\_ncep1d\_anl.sh, pre\_ncep1d\_fct.sh]
  - \$> sh fcst.sh (attention! MPI process number)  
running at "\${NHM}/Work/RF20km"
    - You can see progress in the command below.  
tail -f "\${NHM}/Work/RF20km/log.fcst\_nfx.\${PID}
  - \$> sh end.sh  
output at "\${NHM}/Data/RF20km"






# Visualization by webpandah


- NuSDaS output files:
  - fcst\_const.nus : surface constant file (height, sl, lat, lon...)
  - fcst\_land.nus : skintemp, sst, landuse
  - fcst\_mdl.nus : model-plane forecast variables
  - fcst\_p.nus : p-plane forecast (and diagnostic) variables
  - fcst\_sfc.nus : surface forecast (and diagnostic) variables
  
  - #for monitor
  - fcst\_phy2m.nus : 2-D physical variables monitor
  - fcst\_phy3m.nus : 3-D physical variables monitor





# Result of realistic experiment

- Initial time is 2007-Jul-15 00UTC. Typhoon "MAN-YI" hit Japan.
- For 6hr forecast around Japan (51x51x40 with 20km in horizontal) 10minutes need on this machine.
- So, I have already done this simulation.





# Nhm/Ss/RFnest

(Using results of RF20km execute 1-way nesting-run in 5km)

- 1-way self-nesting shell script.  
(NHM is available 1-way only)
- Almost same as RF20km.
- (See “README” file)
- Edit "**TIMECARD**" same as target DATE
- Edit "**parm.sh**" for your environments
  - Change “**INPUTDIR**” for results of RF20km
  - set “**KTLAG**” and “**FTEND**”
  - and check another settings as in “RF20km/parm.sh”
- If you want to run once more, copy "**RFnest**" and rewrite "**TIMECARD**" and "**parm.sh**".






# Restart-run

- If you have a limitation of CPU-time for continuous run, you should use "restart-run".
- Using "restart", you have to change some parameters in "fcst.sh".
- First of all, you have to prepare special fcst.sh for restart.

## "all.sh" for normal-run

```
sh setup.sh  
sh mkenst.sh  
sh mksfcnst.sh  
sh pre_[jra, ncep].sh  
sh fcst.sh  
sh end.sh
```



## "all.sh" for restart-run

```
sh setup.sh  
sh mkenst.sh  
sh mksfcnst.sh  
sh pre_[jra, ncep].sh  
sh fcst_1.sh  
sh fcst_[2, 3, 4, ...].sh  
sh fcst_end.sh ...  
sh end.sh
```

- Details are shown in the next slide.






# fcst.sh for 1st-run (fcst\_1.sh)

## (output restart files only)

"fcst.sh" for normal-run  
 &NAMPAR  
 ITST=1,ITEND=\${ITEND},ITOU  
 T=5000, ITCHK=1,  
 .....  
 &NAMFIL  
 .....  
 IMT\_RS\_OUT=-1, output\_ninfo =  
 0, ibase\_fake=0,  
 .....



"fcst\_1.sh" for (1st) restart-run  
 &NAMPAR  
 ITST=1,ITEND=\${1<sup>st</sup> restart  
 end in timestep},ITOUT=5000,  
 ITCHK=1,  
 .....  
 &NAMFIL  
 .....  
**IMT\_RS\_OUT=1**, output\_ninfo  
 = 0, ibase\_fake=0,  
 .....


Then, restart-files are output in  
 \${work} directory in each mpi-  
 processes






## fcst.sh for 2nd-run (fcst\_[2, 3,4, ...].sh) (input and output restart files)

"fcst.sh" for normal-run  
 &NAMPAR  
 ITST=1,ITEND=\${ITEND},ITOU  
 T=5000, ITCHK=1,  
 .....  
 &NAMFIL  
 .....  
 IMT\_RS\_OUT=-1, output\_ninfo =  
 0, ibase\_fake=0,  
 .....



"fcst\_2.sh" for (2nd) restart-run  
 &NAMPAR  
 ITST=\${1<sup>st</sup> restart end in  
 timestep},ITEND=\${2<sup>nd</sup> restart  
 end in timestep},ITOUT=5000,  
 ITCHK=1,  
 .....  
 &NAMFIL  
 .....  
 IMT\_RS\_OUT=1,  
 IMT\_RS\_IN=1, output\_ninfo =  
 0, ibase\_fake=0,  
 .....






# fcst.sh for final-run (fcst\_end.sh)

## (end of restart, input restart files only)

```
"fcst.sh" for normal-run
&NAMPAR
ITST=1,ITEND=${ITEND},ITOU
T=5000, ITCHK=1,
.....
&NAMFIL
.....
IMT_RS_OUT=-1, output_ninfo =
0, ibase_fake=0,
.....
```



```
"fcst_end.sh" for end of restart-
run
&NAMPAR
ITST=${previous restart end in
timestep},ITEND=${forecast
end in timestep},ITOUT=5000,
ITCHK=1,
.....
&NAMFIL
.....
IMT_RS_IN=1, output_ninfo =
0, ibase_fake=0,
.....
```





## Note for restart-run

- **Don't change FTEND** in parm.sh from normal run. FTEND show the whole forecast hour in restart.
  - each forecast hour of fcst\_[1,2,..].sh is set in **ITEND**.
- Initial and boundary files are same as normal (continuous) run. You have to prepare whole period for restart-run.
- Don't change MPI-process number in each restart run.
- Restart files are output in  $\{\text{work}\}$  directory and overwrite in each restart run by the same name for each MPI-process.





# under-constructing now

- Execute NHM from "Meteorological Research Consortium" dataset (for collaborative research member with MRI/JMA only)
  - now available “RSMC125 **weekly ensemble forecast (50 members, 1.25degree resolution, 12hourly interval)**“ **global forecast** data set
  - constructing to use "GANAL (**20km resolution, 6hourly interval**)" for initial and boundary on **global analysis**.
  - constructing to use "**monthly ensemble forecast (50 members, 2.5degree resolution, 6hourly interval, once a week)**" **global forecast** data set
  - now available "**MANAL (10km resolution, 3hourly interval)**" for initial and "mfboudary" for boundary **around Japan only**.
- Preparing a convertor from NuSDaS to GRIB and GRIB2.  
(“**NuSDaS to GrADS**” is already available.)

